

From the `config.ini` it is possible to specify the Pointsec Protector Server names and default port number, boot protection passwords, and permission of who is allowed to uninstall the client software. The `config.ini` can be opened and edited using any text editor or `notepad.exe`.

The following information is stored (the default settings are shown):

```
[Server]
Servers=
DefaultPort=9738
ServerOrder=1

[Client]
UsersCanAdmin=0
EM=1 (Removable Media Manager)
EMUPGRADE=0

[Uninstall]
AllowedUsers=%COMPUTER%\Administrator,%DOMAIN%\Administrator
AllowedGroups=%DOMAIN%\Administrators,%DOMAIN%\domain
admins,CHECK POINT\administrators
```

Syntax

[Server] - (Server configuration section)
Servers=Server1:9738;Server2:9738 - (Specify the server names and port number)
DefaultPort=9738 - (Specify the default port number displayed in the server installation dialog)
ServerOrder=1 - (Specifies the server mode - 1=sequential, 2=random)

[Client] - (Client configuration section)
UsersCanAdmin=0 - (Enables the client local administration mode)
EM=1 - (Enables removable media manager enhanced mode disk checking 1=enabled, 0=disabled)
EMUPGRADE=0 - (Determines whether the EM settings are modified during upgrade 1=upgrade, 0=Leave existing settings)

[Uninstall]
AllowedUsers=%COMPUTER%\Administrator,%DOMAIN%\Administrator (If present specifies the users that can uninstall Pointsec Protector client %COMPUTER% denotes the current computer where the software is being installed.
%DOMAIN% denotes the current domain where the software is being installed.
Domain\username can also be used to specify specific domains.)
AllowedGroups=%DOMAIN%\Administrators,%DOMAIN%\domain admins,CHECK POINT\administrators (If present specifies the user groups that can uninstall the Pointsec Protector Client Software)

Example 1

If for example a Pointsec Protector Client is to be installed with the following settings:

- Connecting to Server1 and Server2 on port 9738 sequentially
- Only the username `Dadministrator` and the group `domain admins` on the installed domain can uninstall the software.

```
[Server]
Servers=Server1:9738;Server2:9738
DefaultPort=9738
ServerOrder=1
```

```
[Uninstall]
AllowedUsers=%DOMAIN%\Dadministrator
AllowedGroups=%DOMAIN%\domain admins
```

Example 2

If for example a Pointsec Protector Client is to be installed with the following settings:

- Connecting to Server1 and Server2 on port 9738 randomly
- Only the username `Dadministrator` and the group `domain admins` on the installed domain can uninstall the software. In addition the local user `Administrator` and the user `Administrator` on the Check Point domain are permitted to uninstall.

```
[Server]
Servers=Server1:9738;Server2:9738
DefaultPort=9738
ServerOrder=2
```

```
[Uninstall]
AllowedUsers=%DOMAIN%\Dadministrator,%COMPUTER%\Administrator,
Check Point\Administrator
AllowedGroups=%DOMAIN%\domain admins
```

Example 3

If for example a Pointsec Protector Client is to be installed with the following settings:

- Connecting to Server1 and Server2 on port 9738 randomly
- Only the username `Dadministrator` and the group `domain admins` on the Check Point domain can uninstall the software.

```
[Server]
Servers=Server1:9738;Server2:9738
DefaultPort=9738
ServerOrder=2
```

```
[Uninstall]
AllowedUsers=Check Point\Dnadministrator
AllowedGroups=Check Point\Domain administrators
```